


Boston Butt Joint (Neck End) – boneless and rindless



Code: 2024



1 Make a mark on the first rib 10 mm from the edge of the neck bone and parallel with the backline.



2 Cut and saw through the bones.



3 Separate into Boston Butt (neck end) and remaining hand and spring.



4 Boston Butt (neck end) – bone-in, rind-on



5 Remove rind and back fat.



6 Trim excess fat, maximum fat thickness 10 mm.

Boston Butt Joint (Neck End) – boneless and rindless (continued)

Code: 2024



7 Sheet bone neck and rib bones.



8 Expose the blade bone trying not to cut into surrounding muscles.



9 Remove the blade bone and trim away any bone gristle and cartilage.



10 Trim excess fat to a thickness of 10 mm maximum. Secure joint with string or roasting bands.



11 Boston Butt Joint (neck end) – boneless and rindless.